

#	System Code	Fixit!	Error Message
0	0x0000	N/A	The operation completed successfully.
1	0x0001	N/A	Incorrect function.
2	0x0002	N/A	The <u>system</u> cannot find the file specified.
3	0x0003	N/A	The system cannot find the path specified.
4	0x0004	N/A	The system cannot open the file.
5	0x0005	N/A	Access is denied.
6	0x0006	N/A	The handle is invalid.
7	0x0007	N/A	The storage control blocks were destroyed.
8	0x0008	N/A	Not enough storage is available to process this command.
9	0x0009	N/A	The storage control block address is invalid.
10	0x000A	N/A	The environment is incorrect.
11	0x000B	N/A	An attempt was made to load a program with an incorrect format.
12	0x000C	N/A	The <u>access code</u> is invalid.
13	0x000D	N/A	The <u>data</u> is invalid.
14	0x000E	N/A	Not enough storage is available to complete this operation.
15	0x000F	N/A	The system cannot find the drive specified.
16	0x0010	N/A	The directory cannot be removed.
17	0x0011	N/A	The system cannot move the file to a different <u>disk drive</u> .
18	0x0012	N/A	There are no more files.
19	0x0013	N/A	The media is write protected.
20	0x0014	N/A	The system cannot find the device specified.
21	0x0015	N/A	The device is not ready.
22	0x0016	N/A	The device does not recognize the command.
23	0x0017	N/A	Data error (cyclic redundancy check)
24	0x0018	N/A	The program issued a command but the command length is incorrect.
25	0x0019	N/A	The drive cannot locate a specific area or track on the disk.
26	0x001A	N/A	The specified disk or diskette cannot be accessed.
27	0x001B	N/A	The drive cannot find the sector requested.
28	0x001C	N/A	The <u>printer</u> is out of paper.
29	0x001D	N/A	The system cannot write to the specified device.

30	0x001E	N/A	The system cannot read from the specified device.
31	0x001F	N/A	A device attached to the system is not functioning.
32	0x0020	N/A	The process cannot access the file because it is being used by another process.
33	0x0021	N/A	The process cannot access the file because another process has locked a portion of the file.
34	0x0022	N/A	The wrong diskette is in the drive. Insert %2 (Volume Serial Number: %3) into drive %1.
36	0x0024	N/A	Too many files opened for sharing.
38	0x0026	N/A	Reached end of file.
39	0x0027	N/A	The disk is full.
50	0x0032	N/A	The <u>network</u> request is not supported.
51	0x0033	N/A	The remote <u>computer</u> is not available.
52	0x0034	N/A	A duplicate name exists on the network.
53	0x0035	N/A	The network path was not found.
54	0x0036	N/A	The network is busy.
55	0x0037	N/A	The specified network resource or device is no longer available.
56	0x0038	N/A	The network BIOS command limit has been reached.
57	0x0039	N/A	A network adapter <u>hardware</u> error occurred.
58	0x003A	N/A	The specified <u>server</u> cannot perform the requested operation.
59	0x003B	N/A	An unexpected network error occurred.
60	0x003C	N/A	The remote adapter is not compatible.
61	0x003D	N/A	The printer queue is full.
62	0x003E	N/A	Space to store the file waiting to be printed is not available on the server.
63	0x003F	N/A	Your file waiting to be printed was deleted.
64	0x0040	N/A	The specified network name is no longer available.
65	0x0041	N/A	<u>Network access</u> is denied.
66	0x0042	N/A	The network resource type is not correct.
67	0x0043	N/A	The network name cannot be found.
68	0x0044	N/A	The name limit for the local <u>computer network</u> adapter card was exceeded.
69	0x0045	N/A	The network BIOS session limit was exceeded.
70	0x0046	N/A	The <u>remote server</u> has been paused or is in the process of being started.
71	0x0047	N/A	No more connections can be made to this remote <u>computer</u> at this time because there are already as many connections as the <u>computer</u> can accept.

72	0x0048	N/A	The specified printer or disk device has been paused.
80	0x0050	N/A	The file exists.
82	0x0052	N/A	The directory or file cannot be created.
83	0x0053	N/A	Fail on INT 24
84	0x0054	N/A	Storage to process this request is not available.
85	0x0055	N/A	The local device name is already in use.
86	0x0056	N/A	The specified <u>network password</u> is not correct.
87	0x0057	N/A	The parameter is incorrect.
88	0x0058	N/A	A write fault occurred on the network.
89	0x0059	N/A	The system cannot start another process at this time.
100	0x0064	N/A	Cannot create another system semaphore.
101	0x0065	N/A	The exclusive semaphore is owned by another process.
102	0x0066	N/A	The semaphore is set and cannot be closed.
103	0x0067	N/A	The semaphore cannot be set again.
104	0x0068	N/A	Cannot request exclusive semaphores at interrupt time.
105	0x0069	N/A	The previous ownership of this semaphore has ended.
106	0x006A	N/A	Insert the diskette for drive %1.
107	0x006B	N/A	Program stopped because alternate diskette was not inserted.
108	0x006C	N/A	The disk is in use or locked by another process.
109	0x006D	N/A	The pipe has been ended.
110	0x006E	N/A	The system cannot open the device or file specified.
111	0x006F	N/A	The file name is too long.
112	0x0070	N/A	There is not enough space on the disk.
113	0x0071	N/A	No more internal file identifiers available.
114	0x0072	N/A	The target internal file identifier is incorrect.
117	0x0075	N/A	The IOCTL call made by the <u>application program</u> is not correct.
118	0x0076	N/A	The verify-on-write switch parameter value is not correct.
119	0x0077	N/A	The system does not support the command requested.
120	0x0078	N/A	This function is only valid in Win32 mode.
121	0x0079	N/A	The semaphore timeout period has expired.
122	0x007A	N/A	The data area passed to a system call is too small.
123	0x007B	N/A	The filename, directory name, or volume label syntax is incorrect.
124	0x007C	N/A	The system call level is not correct.
125	0x007D	N/A	The disk has no volume label.

126	0x007E	N/A	The specified module could not be found.
127	0x007F	N/A	The specified procedure could not be found.
128	0x0080	N/A	There are no child processes to wait for.
129	0x0081	N/A	The %1 <u>application</u> cannot be run in Win32 mode.
130	0x0082	N/A	Attempt to use a file handle to an open <u>disk partition</u> for an operation other than raw disk I/O.
131	0x0083	N/A	An attempt was made to move the file pointer before the beginning of the file.
132	0x0084	N/A	The file pointer cannot be set on the specified device or file.
133	0x0085	N/A	A JOIN or SUBST command cannot be used for a drive that contains previously joined drives.
134	0x0086	N/A	An attempt was made to use a JOIN or SUBST command on a drive that has already been joined.
135	0x0087	N/A	An attempt was made to use a JOIN or SUBST command on a drive that has already been substituted.
136	0x0088	N/A	The system tried to delete the JOIN of a drive that is not joined.
137	0x0089	N/A	The system tried to delete the substitution of a drive that is not substituted.
138	0x008A	N/A	The system tried to join a drive to a directory on a joined drive.
139	0x008B	N/A	The system tried to substitute a drive to a directory on a substituted drive.
140	0x008C	N/A	The system tried to join a drive to a directory on a substituted drive.
141	0x008D	N/A	The system tried to SUBST a drive to a directory on a joined drive.
142	0x008E	N/A	The system cannot perform a JOIN or SUBST at this time.
143	0x008F	N/A	The system cannot join or substitute a drive to or for a directory on the same drive.
144	0x0090	N/A	The directory is not a subdirectory of the root directory.
145	0x0091	N/A	The directory is not empty.
146	0x0092	N/A	The path specified is being used in a substitute.
147	0x0093	N/A	Not enough resources are available to process this command.
148	0x0094	N/A	The path specified cannot be used at this time.
149	0x0095	N/A	An attempt was made to join or substitute a drive for which a directory on the drive is the target of a previous substitute.
150	0x0096	N/A	System trace information was not specified in your CONFIG.SYS file, or tracing is disallowed.
151	0x0097	N/A	The number of specified semaphore events for DosMuxSemWait is not correct.
152	0x0098	N/A	DosMuxSemWait did not execute; too many semaphores are already set.
153	0x0099	N/A	The DosMuxSemWait list is not correct.

154	0x009A	N/A	The volume label you entered exceeds the label character limit of the target <u>file system</u> .
155	0x009B	N/A	Cannot create another thread.
156	0x009C	N/A	The recipient process has refused the signal.
157	0x009D	N/A	The segment is already discarded and cannot be locked.
158	0x009E	N/A	The segment is already unlocked.
159	0x009F	N/A	The address for the thread ID is not correct.
160	0x00A0	N/A	The argument string passed to DosExecPgm is not correct.
161	0x00A1	N/A	The specified path is invalid.
162	0x00A2	N/A	A signal is already pending.
164	0x00A4	N/A	No more threads can be created in the system.
167	0x00A7	N/A	Unable to lock a region of a file.
170	0x00AA	N/A	The requested resource is in use.
173	0x00AD	N/A	A lock request was not outstanding for the supplied cancel region.
174	0x00AE	N/A	The file system does not support atomic changes to the lock type.
180	0x00B4	N/A	The system detected a segment number that was not correct.
182	0x00B6	N/A	The <u>operating system</u> cannot run %1.
183	0x00B7	N/A	Cannot create a file when that file already exists.
186	0x00BA	N/A	The flag passed is not correct.
187	0x00BB	N/A	The specified system semaphore name was not found.
188	0x00BC	N/A	The operating system cannot run %1.
189	0x00BD	N/A	The operating system cannot run %1.
190	0x00BE	N/A	The operating system cannot run %1.
191	0x00BF	N/A	Cannot run %1 in Win32 mode.
192	0x00C0	N/A	The operating system cannot run %1.
193	0x00C1	N/A	%1 is not a valid Win32 application.
194	0x00C2	N/A	The operating system cannot run %1.
195	0x00C3	N/A	The operating system cannot run %1.
196	0x00C4	N/A	The operating system cannot run this application program.
197	0x00C5	N/A	The operating system is not presently configured to run this application.
198	0x00C6	N/A	The operating system cannot run %1.
199	0x00C7	N/A	The operating system cannot run this application program.
200	0x00C8	N/A	The code segment cannot be greater than or equal to 64KB.
201	0x00C9	N/A	The operating system cannot run %1.

202	0x00CA	N/A	The operating system cannot run %1.
203	0x00CB	N/A	The system could not find the environment option that was entered.
205	0x00CD	N/A	No process in the command subtree has a signal handler.
206	0x00CE	N/A	The filename or extension is too long.
207	0x00CF	N/A	The ring 2 stack is in use.
208	0x00D0	N/A	The global filename characters, * or ?, are entered incorrectly or too many global filename characters are specified.
209	0x00D1	N/A	The signal being posted is not correct.
210	0x00D2	N/A	The signal handler cannot be set.
212	0x00D4	N/A	The segment is locked and cannot be reallocated.
214	0x00D6	N/A	Too many dynamic link modules are attached to this program or dynamic link module.
215	0x00D7	N/A	Can't nest calls to LoadModule.
230	0x00E6	N/A	The pipe state is invalid.
231	0x00E7	N/A	All pipe instances are busy.
232	0x00E8	N/A	The pipe is being closed.
233	0x00E9	N/A	No process is on the other end of the pipe.
234	0x00EA	N/A	More data is available.
240	0x00F0	N/A	The session was cancelled.
254	0x00FE	N/A	The specified extended attribute name was invalid.
255	0x00FF	N/A	The extended attributes are inconsistent.
259	0x0103	N/A	No more data is available.
266	0x010A	N/A	The Copy API cannot be used.
267	0x010B	N/A	The directory name is invalid.
275	0x0113	N/A	The extended attributes did not fit in the buffer.
276	0x0114	N/A	The extended attribute file on the mounted file system is corrupt.
277	0x0115	N/A	The extended attribute table file is full.
278	0x0116	N/A	The specified extended attribute handle is invalid.
282	0x011A	N/A	The mounted file system does not support extended attributes.
288	0x0120	N/A	Attempt to release mutex not owned by caller.
298	0x012A	N/A	Too many posts were made to a semaphore.
299	0x012B	N/A	Only part of a Read/WriteProcessMemory request was completed.
317	0x013D	N/A	The system cannot find message for message number 0x%1 in message file for %2.
487	0x01E7	N/A	Attempt to access invalid address.

534	0x0216	N/A	Arithmetic result exceeded <u>32 bits</u> .
535	0x0217	N/A	There is a process on other end of the pipe.
536	0x0218	N/A	Waiting for a process to open the other end of the pipe.
994	0x03E2	N/A	Access to the extended attribute was denied.
995	0x03E3	N/A	The I/O operation has been aborted because of either a thread exit or an application request.
996	0x03E4	N/A	Overlapped I/O event is not in a signalled state.
997	0x03E5	N/A	Overlapped I/O operation is in progress.
998	0x03E6	N/A	Invalid access to memory location.
999	0x03E7	N/A	Error performing inpage operation.
1001	0x03E9	N/A	Recursion too deep, stack overflowed.
1002	0x03EA	N/A	The window cannot act on the sent message.
1003	0x03EB	N/A	Cannot complete this function.
1004	0x03EC	N/A	Invalid flags.
1005	0x03ED	N/A	The volume does not contain a recognized file system. Please make sure that all required file system drivers are loaded and that the volume is not corrupt.
1006	0x03EE	N/A	The volume for a file has been externally altered such that the opened file is no longer valid.
1007	0x03EF	N/A	The requested operation cannot be performed in full-screen mode.
1008	0x03F0	N/A	An attempt was made to reference a token that does not exist.
1009	0x03F1	N/A	The configuration registry database is corrupt.
1010	0x03F2	N/A	The configuration <u>registry key</u> is invalid.
1011	0x03F3	N/A	The configuration registry key could not be opened.
1012	0x03F4	N/A	The configuration registry key could not be read.
1013	0x03F5	N/A	The configuration registry key could not be written.
1014	0x03F6	N/A	One of the files in the Registry database had to be recovered by use of a log or alternate copy. The recovery was successful.
1015	0x03F7	N/A	The Registry is corrupt. The structure of one of the files that contains Registry data is corrupt, or the system's image of the file in memory is corrupt, or the file could not be recovered because the alternate copy or log was absent or corrupt.
1016	0x03F8	N/A	An I/O operation initiated by the Registry failed unrecoverably. The Registry could not read in, or write out, or flush, one of the files that contain the system's image of the Registry.
1017	0x03F9	N/A	The system has attempted to load or restore a file into the Registry, but the specified file is not in a Registry <u>file format</u> .
1018	0x03FA	N/A	Illegal operation attempted on a Registry key which has been marked for deletion.

1019	0x03FB	N/A	System could not allocate the required space in a Registry log.
1020	0x03FC	N/A	Cannot create a symbolic link in a Registry key that already has subkeys or values.
1021	0x03FD	N/A	Cannot create a stable subkey under a volatile parent key.
1022	0x03FE	N/A	A notify change request is being completed and the information is not being returned in the caller's buffer. The caller now needs to enumerate the files to find the changes.
1051	0x041B	N/A	A stop control has been sent to a service which other running services are dependent on.
1052	0x041C	N/A	The requested control is not valid for this service
1053	0x041D	N/A	The service did not respond to the start or control request in a timely fashion.
1054	0x041E	N/A	A thread could not be created for the service.
1055	0x041F	N/A	The service database is locked.
1056	0x0420	N/A	An instance of the service is already running.
1057	0x0421	N/A	The account name is invalid or does not exist.
1058	0x0422	N/A	The specified service is disabled and cannot be started.
1059	0x0423	N/A	Circular service dependency was specified.
1060	0x0424	N/A	The specified service does not exist as an installed service.
1061	0x0425	N/A	The service cannot accept control messages at this time.
1062	0x0426	N/A	The service has not been started.
1063	0x0427	N/A	The service process could not connect to the service controller.
1064	0x0428	N/A	An exception occurred in the service when handling the control request.
1065	0x0429	N/A	The database specified does not exist.
1066	0x042A	N/A	The service has returned a service-specific error code .
1067	0x042B	N/A	The process terminated unexpectedly.
1068	0x042C	N/A	The dependency service or group failed to start.
1069	0x042D	N/A	The service did not start due to a logon failure.
1070	0x042E	N/A	After starting, the service hung in a start-pending state.
1071	0x042F	N/A	The specified service database lock is invalid.
1072	0x0430	N/A	The specified service has been marked for deletion.
1073	0x0431	N/A	The specified service already exists.
1074	0x0432	N/A	The system is currently running with the last-known-good configuration.
1075	0x0433	N/A	The dependency service does not exist or has been marked for deletion.
1076	0x0434	N/A	The current boot has already been accepted for use as the last-known-good control set.

1077	0x0435	N/A	No attempts to start the service have been made since the last boot.
1078	0x0436	N/A	The name is already in use as either a service name or a service display name.
1100	0x044C	N/A	The physical end of the tape has been reached.
1101	0x044D	N/A	A tape access reached a filemark.
1102	0x044E	N/A	Beginning of tape or partition was encountered.
1103	0x044F	N/A	A tape access reached the end of a set of files.
1104	0x0450	N/A	No more data is on the tape.
1105	0x0451	N/A	Tape could not be partitioned.
1106	0x0452	N/A	When accessing a new tape of a multivolume partition, the current blocksize is incorrect.
1107	0x0453	N/A	Tape partition information could not be found when loading a tape.
1108	0x0454	N/A	Unable to lock the media eject mechanism.
1109	0x0455	N/A	Unable to unload the media.
1110	0x0456	N/A	Media in drive may have changed.
1111	0x0457	N/A	The I/O bus was reset.
1112	0x0458	N/A	No media in drive.
1113	0x0459	N/A	No mapping for the Unicode character exists in the target multi-byte code page .
1114	0x045A	N/A	A dynamic link library (DLL) initialization routine failed.
1115	0x045B	N/A	A system shutdown is in progress.
1116	0x045C	N/A	Unable to abort the system shutdown because no shutdown was in progress.
1117	0x045D	N/A	The request could not be performed because of an I/O device error.
1118	0x045E	N/A	No serial device was successfully initialized. The serial driver will unload.
1119	0x045F	N/A	Unable to open a device that was sharing an interrupt request (IRQ) with other devices. At least one other device that uses that IRQ was already opened.
1120	0x0460	N/A	A serial I/O operation was completed by another write to the serial port . (The IOCTL_SERIAL_XOFF_COUNTER reached zero.)
1121	0x0461	N/A	A serial I/O operation completed because the time-out period expired. (The IOCTL_SERIAL_XOFF_COUNTER did not reach zero.)
1122	0x0462	N/A	No ID address mark was found on the floppy disk.
1123	0x0463	N/A	Mismatch between the floppy disk sector ID field and the floppy disk controller track address.
1124	0x0464	N/A	The floppy disk controller reported an error that is not recognized by the floppy disk driver.
1125	0x0465	N/A	The floppy disk controller returned inconsistent results in its registers.

1126	0x0466	N/A	While accessing the <u>hard disk</u> , a recalibrate operation failed, even after retries.
1127	0x0467	N/A	While accessing the hard disk, a disk operation failed even after retries.
1128	0x0468	N/A	While accessing the hard disk, a disk controller reset was needed, but even that failed.
1129	0x0469	N/A	Physical end of tape encountered.
1130	0x046A	N/A	Not enough <u>server storage</u> is available to process this command.
1131	0x046B	N/A	A potential deadlock condition has been detected.
1132	0x046C	N/A	The base address or the file offset specified does not have the proper alignment.
1140	0x0474	N/A	An attempt to change the system power state was vetoed by another application or driver.
1141	0x0475	N/A	The system BIOS failed an attempt to change the system power state.
1150	0x047E	N/A	The specified program requires a newer version of Windows.
1151	0x047F	N/A	The specified program is not a Windows or MS-DOS program.
1152	0x0480	N/A	Cannot start more than one instance of the specified program.
1153	0x0481	N/A	The specified program was written for an older version of Windows.
1154	0x0482	N/A	One of the library files needed to run this application is damaged.
1155	0x0483	N/A	No application is associated with the specified file for this operation.
1156	0x0484	N/A	An error occurred in sending the command to the application.
1157	0x0485	N/A	One of the library files needed to run this application cannot be found.
1200	0x04B0	N/A	The specified device name is invalid.
1201	0x04B1	N/A	The device is not currently connected but it is a remembered connection.
1202	0x04B2	N/A	An attempt was made to remember a device that had previously been remembered.
1203	0x04B3	N/A	No <u>network provider</u> accepted the given network path.
1204	0x04B4	N/A	The specified network provider name is invalid.
1205	0x04B5	N/A	Unable to open the <u>network connection</u> profile.
1206	0x04B6	N/A	The network connection profile is corrupt.
1207	0x04B7	N/A	Cannot enumerate a non-container.
1208	0x04B8	N/A	An extended error has occurred.
1209	0x04B9	N/A	The format of the specified group name is invalid.
1210	0x04BA	N/A	The format of the specified <u>computer</u> name is invalid.
1211	0x04BB	N/A	The format of the specified event name is invalid.
1212	0x04BC	N/A	The format of the specified <u>domain name</u> is invalid.

1213	0x04BD	N/A	The format of the specified service name is invalid.
1214	0x04BE	N/A	The format of the specified network name is invalid.
1215	0x04BF	N/A	The format of the specified share name is invalid.
1216	0x04C0	N/A	The format of the specified password is invalid.
1217	0x04C1	N/A	The format of the specified message name is invalid.
1218	0x04C2	N/A	The format of the specified message destination is invalid.
1219	0x04C3	N/A	The credentials supplied conflict with an existing set of credentials.
1220	0x04C4	N/A	An attempt was made to establish a session to a <u>network server</u> , but there are already too many sessions established to that server.
1221	0x04C5	N/A	The workgroup or domain name is already in use by another <u>computer</u> on the network.
1222	0x04C6	N/A	The network is not present or not started.
1223	0x04C7	N/A	The operation was cancelled by the user.
1224	0x04C8	N/A	The requested operation cannot be performed on a file with a user mapped section open.
1225	0x04C9	N/A	The <u>remote system</u> refused the network connection.
1226	0x04CA	N/A	The network connection was gracefully closed.
1227	0x04CB	N/A	The network transport endpoint already has an address associated with it.
1228	0x04CC	N/A	An address has not yet been associated with the network endpoint.
1229	0x04CD	N/A	An operation was attempted on a non-existent network connection.
1230	0x04CE	N/A	An invalid operation was attempted on an active network connection.
1231	0x04CF	N/A	The remote network is not reachable by the transport.
1232	0x04D0	N/A	The remote system is not reachable by the transport.
1233	0x04D1	N/A	The remote system does not support the transport protocol.
1234	0x04D2	N/A	No service is operating at the destination network endpoint on the remote system.
1235	0x04D3	N/A	The request was aborted.
1236	0x04D4	N/A	The network connection was aborted by the local system.
1237	0x04D5	N/A	The operation could not be completed. A retry should be performed.
1238	0x04D6	N/A	A connection to the server could not be made because the limit on the number of concurrent connections for this account has been reached.
1239	0x04D7	N/A	Attempting to login during an unauthorized time of day for this account.
1240	0x04D8	N/A	The account is not authorized to login from this station.
1241	0x04D9	N/A	The network address could not be used for the operation requested.
1242	0x04DA	N/A	The service is already registered.

1243	0x04DB	N/A	The specified service does not exist.
1244	0x04DC	N/A	The operation being requested was not performed because the user has not been authenticated.
1245	0x04DD	N/A	The operation being requested was not performed because the user has not logged on to the network. The specified service does not exist.
1246	0x04DE	N/A	Return that wants caller to continue with work in progress.
1247	0x04DF	N/A	An attempt was made to perform an initialization operation when initialization has already been completed.
1248	0x04E0	N/A	No more local devices.
1300	0x0514	N/A	Not all privileges referenced are assigned to the caller.
1301	0x0515	N/A	Some mapping between account names and security IDs was not done.
1302	0x0516	N/A	No system quota limits are specifically set for this account.
1303	0x0517	N/A	No encryption key is available. A well-known encryption key was returned.
1304	0x0518	N/A	The NT password is too complex to be converted to a LAN Manager password. The LAN Manager password returned is a NULL string.
1305	0x0519	N/A	The revision level is unknown.
1306	0x051A	N/A	Indicates two revision levels are incompatible.
1307	0x051B	N/A	This security ID may not be assigned as the owner of this object.
1308	0x051C	N/A	This security ID may not be assigned as the primary group of an object.
1309	0x051D	N/A	An attempt has been made to operate on an impersonation token by a thread that is not currently impersonating a client.
1310	0x051E	N/A	The group may not be disabled.
1311	0x051F	N/A	There are currently no logon servers available to service the logon request.
1312	0x0520	N/A	A specified logon session does not exist. It may already have been terminated.
1313	0x0521	N/A	A specified privilege does not exist.
1314	0x0522	N/A	A required privilege is not held by the client.
1315	0x0523	N/A	The name provided is not a properly formed account name.
1316	0x0524	N/A	The specified user already exists.
1317	0x0525	N/A	The specified user does not exist.
1318	0x0526	N/A	The specified group already exists.
1319	0x0527	N/A	The specified group does not exist.
1320	0x0528	N/A	Either the specified user account is already a member of the specified group, or the specified group cannot be deleted because it contains a member.
1321	0x0529	N/A	The specified user account is not a member of the specified group account.

1322	0x052A	N/A	The last remaining administration account cannot be disabled or deleted.
1323	0x052B	N/A	Unable to update the password. The value provided as the current password is incorrect.
1324	0x052C	N/A	Unable to update the password. The value provided for the new password contains values that are not allowed in passwords.
1325	0x052D	N/A	Unable to update the password because a password update rule has been violated.
1326	0x052E	N/A	Logon failure: unknown user name or bad password.
1327	0x052F	N/A	Logon failure: user account restriction.
1328	0x0530	N/A	Logon failure: account logon time restriction violation.
1329	0x0531	N/A	Logon failure: user not allowed to log on to this <u>computer</u> .
1330	0x0532	N/A	Logon failure: the specified account password has expired.
1331	0x0533	N/A	Logon failure: account currently disabled.
1332	0x0534	N/A	No mapping between account names and security IDs was done.
1333	0x0535	N/A	Too many local user identifiers (LUIDs) were requested at one time.
1334	0x0536	N/A	No more local user identifiers (LUIDs) are available.
1335	0x0537	N/A	The subauthority part of a security ID is invalid for this particular use.
1336	0x0538	N/A	The <u>access control</u> list (ACL) structure is invalid.
1337	0x0539	N/A	The security ID structure is invalid.
1338	0x053A	N/A	The <u>security</u> descriptor structure is invalid.
1340	0x053C	N/A	The inherited access control list (ACL) or access control entry (ACE) could not be built.
1341	0x053D	N/A	The server is currently disabled.
1342	0x053E	N/A	The server is currently enabled.
1343	0x053F	N/A	The value provided was an invalid value for an identifier authority.
1344	0x0540	N/A	No more memory is available for security information updates.
1345	0x0541	N/A	The specified attributes are invalid, or incompatible with the attributes for the group as a whole.
1346	0x0542	N/A	Either a required impersonation level was not provided, or the provided impersonation level is invalid.
1347	0x0543	N/A	Cannot open an anonymous level <u>security token</u> .
1348	0x0544	N/A	The validation information class requested was invalid.
1349	0x0545	N/A	The type of the token is inappropriate for its attempted use.
1350	0x0546	N/A	Unable to perform a security operation on an object which has no associated security.
1351	0x0547	N/A	Indicates a <u>Windows NT Server</u> could not be contacted or that objects within the <u>domain</u> are protected such that necessary information could not be retrieved.

1352	0x0548	N/A	The security account manager (SAM) or local security authority (LSA) server was in the wrong state to perform the security operation.
1353	0x0549	N/A	The domain was in the wrong state to perform the security operation.
1354	0x054A	N/A	This operation is only allowed for the Primary Domain Controller of the domain.
1355	0x054B	N/A	The specified domain did not exist.
1356	0x054C	N/A	The specified domain already exists.
1357	0x054D	N/A	An attempt was made to exceed the limit on the number of domains per server.
1358	0x054E	N/A	Unable to complete the requested operation because of either a catastrophic media failure or a data structure corruption on the disk.
1359	0x054F	N/A	The security account database contains an internal inconsistency.
1360	0x0550	N/A	Generic access types were contained in an access mask which should already be mapped to non-generic types.
1361	0x0551	N/A	A security descriptor is not in the right format (absolute or self-relative).
1362	0x0552	N/A	The requested action is restricted for use by logon processes only. The calling process has not registered as a logon process.
1363	0x0553	N/A	Cannot start a new logon session with an ID that is already in use.
1364	0x0554	N/A	A specified authentication package is unknown.
1365	0x0555	N/A	The logon session is not in a state that is consistent with the requested operation.
1366	0x0556	N/A	The logon session ID is already in use.
1367	0x0557	N/A	A logon request contained an invalid logon type value.
1368	0x0558	N/A	Unable to impersonate via a named pipe until data has been read from that pipe.
1369	0x0559	N/A	The transaction state of a Registry subtree is incompatible with the requested operation.
1370	0x055A	N/A	An internal security database corruption has been encountered.
1371	0x055B	N/A	Cannot perform this operation on built-in accounts.
1372	0x055C	N/A	Cannot perform this operation on this built-in special group.
1373	0x055D	N/A	Cannot perform this operation on this built-in special user.
1374	0x055E	N/A	The user cannot be removed from a group because the group is currently the user's primary group.
1375	0x055F	N/A	The token is already in use as a primary token.
1376	0x0560	N/A	The specified local group does not exist.
1377	0x0561	N/A	The specified account name is not a member of the local group.
1378	0x0562	N/A	The specified account name is already a member of the local group.
1379	0x0563	N/A	The specified local group already exists.

1380	0x0564	N/A	Logon failure: the user has not been granted the requested logon type at this <u>computer</u> .
1381	0x0565	N/A	The maximum number of secrets that may be stored in a single system has been exceeded.
1382	0x0566	N/A	The length of a secret exceeds the maximum length allowed.
1383	0x0567	N/A	The local security authority database contains an internal inconsistency.
1384	0x0568	N/A	During a logon attempt, the user's security context accumulated too many security IDs.
1385	0x0569	N/A	Logon failure: the user has not been granted the requested logon type at this <u>computer</u> .
1386	0x056A	N/A	A cross-encrypted password is necessary to change a user password.
1387	0x056B	N/A	A new member could not be added to a local group because the member does not exist.
1388	0x056C	N/A	A new member could not be added to a local group because the member has the wrong account type.
1389	0x056D	N/A	Too many security IDs have been specified.
1390	0x056E	N/A	A cross-encrypted password is necessary to change this user password.
1391	0x056F	N/A	Indicates an ACL contains no inheritable components
1392	0x0570	N/A	The file or directory is corrupt and non-readable.
1393	0x0571	N/A	The disk structure is corrupt and non-readable.
1394	0x0572	N/A	There is no user session key for the specified logon session.
1395	0x0573	N/A	The service being accessed is licensed for a particular number of connections. No more connections can be made to the service at this time because there are already as many connections as the service can accept.
1400	0x0578	N/A	Invalid window handle.
1401	0x0579	N/A	Invalid menu handle.
1402	0x057A	N/A	Invalid <u>cursor</u> handle.
1403	0x057B	N/A	Invalid accelerator table handle.
1404	0x057C	N/A	Invalid hook handle.
1405	0x057D	N/A	Invalid handle to a multiple-window position structure.
1406	0x057E	N/A	Cannot create a top-level child window.
1407	0x057F	N/A	Cannot find window class.
1408	0x0580	N/A	Invalid window, belongs to other thread.
1409	0x0581	N/A	Hot key is already registered.
1410	0x0582	N/A	Class already exists.
1411	0x0583	N/A	Class does not exist.

1412	0x0584	N/A	Class still has open windows.
1413	0x0585	N/A	Invalid index.
1414	0x0586	N/A	Invalid icon handle.
1415	0x0587	N/A	Using private DIALOG window words.
1416	0x0588	N/A	The listbox identifier was not found.
1417	0x0589	N/A	No wildcards were found.
1418	0x058A	N/A	Thread does not have a clipboard open.
1419	0x058B	N/A	Hot key is not registered.
1420	0x058C	N/A	The window is not a valid dialog window.
1421	0x058D	N/A	Control ID not found.
1422	0x058E	N/A	Invalid message for a combo box because it does not have an edit control.
1423	0x058F	N/A	The window is not a combo box.
1424	0x0590	N/A	Height must be less than 256.
1425	0x0591	N/A	Invalid device context (DC) handle.
1426	0x0592	N/A	Invalid hook procedure type.
1427	0x0593	N/A	Invalid hook procedure.
1428	0x0594	N/A	Cannot set non-local hook without a module handle.
1429	0x0595	N/A	This hook procedure can only be set globally.
1430	0x0596	N/A	The journal hook procedure is already installed.
1431	0x0597	N/A	The hook procedure is not installed.
1432	0x0598	N/A	Invalid message for single-selection listbox.
1433	0x0599	N/A	LB_SETCOUNT sent to non-lazy listbox.
1434	0x059A	N/A	This list box does not support tab stops.
1435	0x059B	N/A	Cannot destroy object created by another thread.
1436	0x059C	N/A	Child windows cannot have menus.
1437	0x059D	N/A	The window does not have a system menu.
1438	0x059E	N/A	Invalid message box style.
1439	0x059F	N/A	Invalid system-wide (SPI_*) parameter.
1440	0x05A0	N/A	Screen already locked.
1441	0x05A1	N/A	All handles to windows in a multiple-window position structure must have the same parent.
1442	0x05A2	N/A	The window is not a child window.
1443	0x05A3	N/A	Invalid GW_* command.
1444	0x05A4	N/A	Invalid thread identifier.

1445	0x05A5	N/A	Cannot process a message from a window that is not a multiple <u>document</u> interface (MDI) window.
1446	0x05A6	N/A	<u>Popup menu</u> already active.
1447	0x05A7	N/A	The window does not have scroll bars.
1448	0x05A8	N/A	Scroll bar range cannot be greater than 0x7FFF.
1449	0x05A9	N/A	Cannot show or remove the window in the way specified.
1450	0x05AA	N/A	Insufficient system resources exist to complete the requested service.
1451	0x05AB	N/A	Insufficient system resources exist to complete the requested service.
1452	0x05AC	N/A	Insufficient system resources exist to complete the requested service.
1453	0x05AD	N/A	Insufficient quota to complete the requested service.
1454	0x05AE	N/A	Insufficient quota to complete the requested service.
1455	0x05AF	N/A	The paging file is too small for this operation to complete.
1456	0x05B0	N/A	A menu item was not found.
1500	0x05DC	N/A	The event log file is corrupt.
1501	0x05DD	N/A	No event log file could be opened, so the event logging service did not start.
1502	0x05DE	N/A	The event log file is full.
1503	0x05DF	N/A	The event log file has changed between reads.
1700	0x06A4	N/A	The string binding is invalid.
1701	0x06A5	N/A	The binding handle is not the correct type.
1702	0x06A6	N/A	The binding handle is invalid.
1703	0x06A7	N/A	The RPC protocol sequence is not supported.
1704	0x06A8	N/A	The RPC protocol sequence is invalid.
1705	0x06A9	N/A	The string universal unique identifier (UUID) is invalid.
1706	0x06AA	N/A	The endpoint format is invalid.
1707	0x06AB	N/A	The network address is invalid.
1708	0x06AC	N/A	No endpoint was found.
1709	0x06AD	N/A	The timeout value is invalid.
1710	0x06AE	N/A	The object universal unique identifier (UUID) was not found.
1711	0x06AF	N/A	The object universal unique identifier (UUID) has already been registered.
1712	0x06B0	N/A	The type universal unique identifier (UUID) has already been registered.
1713	0x06B1	N/A	The RPC server is already listening.
1714	0x06B2	N/A	No protocol sequences have been registered.
1715	0x06B3	N/A	The RPC server is not listening.

1716	0x06B4	N/A	The manager type is unknown.
1717	0x06B5	N/A	The interface is unknown.
1718	0x06B6	N/A	There are no bindings.
1719	0x06B7	N/A	There are no protocol sequences.
1720	0x06B8	N/A	The endpoint cannot be created.
1721	0x06B9	N/A	Not enough resources are available to complete this operation.
1722	0x06BA	N/A	The RPC server is unavailable.
1723	0x06BB	N/A	The RPC server is too busy to complete this operation.
1724	0x06BC	N/A	The network options are invalid.
1725	0x06BD	N/A	There is not a remote procedure call active in this thread.
1726	0x06BE	N/A	The remote procedure call failed.
1727	0x06BF	N/A	The remote procedure call failed and did not execute.
1728	0x06C0	N/A	A remote procedure call (RPC) protocol error occurred.
1730	0x06C2	N/A	The transfer syntax is not supported by the RPC server.
1732	0x06C4	N/A	The universal unique identifier (UUID) type is not supported.
1733	0x06C5	N/A	The tag is invalid.
1734	0x06C6	N/A	The array bounds are invalid.
1735	0x06C7	N/A	The binding does not contain an entry name.
1736	0x06C8	N/A	The name syntax is invalid.
1737	0x06C9	N/A	The name syntax is not supported.
1739	0x06CB	N/A	No network address is available to use to construct a universal unique identifier (UUID).
1740	0x06CC	N/A	The endpoint is a duplicate.
1741	0x06CD	N/A	The authentication type is unknown.
1742	0x06CE	N/A	The maximum number of calls is too small.
1743	0x06CF	N/A	The string is too long.
1744	0x06D0	N/A	The RPC protocol sequence was not found.
1745	0x06D1	N/A	The procedure number is out of range.
1746	0x06D2	N/A	The binding does not contain any authentication information.
1747	0x06D3	N/A	The authentication service is unknown.
1748	0x06D4	N/A	The authentication level is unknown.
1749	0x06D5	N/A	The security context is invalid.
1750	0x06D6	N/A	The authorization service is unknown.
1751	0x06D7	N/A	The entry is invalid.

1752	0x06D8	N/A	The server endpoint cannot perform the operation.
1753	0x06D9	N/A	There are no more endpoints available from the endpoint mapper.
1754	0x06DA	N/A	No interfaces have been exported.
1755	0x06DB	N/A	The entry name is incomplete.
1756	0x06DC	N/A	The version option is invalid.
1757	0x06DD	N/A	There are no more members.
1758	0x06DE	N/A	There is nothing to unexport.
1759	0x06DF	N/A	The interface was not found.
1760	0x06E0	N/A	The entry already exists.
1761	0x06E1	N/A	The entry is not found.
1762	0x06E2	N/A	The name service is unavailable.
1763	0x06E3	N/A	The network address family is invalid.
1764	0x06E4	N/A	The requested operation is not supported.
1765	0x06E5	N/A	No security context is available to allow impersonation.
1766	0x06E6	N/A	An internal error occurred in a remote procedure call (RPC).
1767	0x06E7	N/A	The RPC server attempted an integer division by zero.
1768	0x06E8	N/A	An addressing error occurred in the RPC server.
1769	0x06E9	N/A	A floating-point operation at the RPC server caused a division by zero.
1770	0x06EA	N/A	A floating-point underflow occurred at the RPC server.
1771	0x06EB	N/A	A floating-point overflow occurred at the RPC server.
1772	0x06EC	N/A	The list of RPC servers available for the binding of auto handles has been exhausted.
1773	0x06ED	N/A	Unable to open the character translation table file.
1774	0x06EE	N/A	The file containing the character translation table has fewer than 512 bytes.
1775	0x06EF	N/A	A null context handle was passed from the client to the host during a remote procedure call.
1777	0x06F1	N/A	The context handle changed during a remote procedure call.
1778	0x06F2	N/A	The binding handles passed to a remote procedure call do not match.
1779	0x06F3	N/A	The stub is unable to get the remote procedure call handle.
1780	0x06F4	N/A	A null reference pointer was passed to the stub.
1781	0x06F5	N/A	The enumeration value is out of range.
1782	0x06F6	N/A	The byte count is too small.
1783	0x06F7	N/A	The stub received bad data.
1784	0x06F8	N/A	The supplied user buffer is not valid for the requested operation.

1785	0x06F9	N/A	The disk media is not recognized. It may not be formatted.
1786	0x06FA	N/A	The workstation does not have a trust secret.
1787	0x06FB	N/A	The SAM database on the Windows NT Server does not have a computer account for this workstation trust relationship.
1788	0x06FC	N/A	The trust relationship between the primary domain and the trusted domain failed.
1789	0x06FD	N/A	The trust relationship between this workstation and the primary domain failed.
1790	0x06FE	N/A	The network logon failed.
1791	0x06FF	N/A	A remote procedure call is already in progress for this thread.
1792	0x0700	N/A	An attempt was made to logon, but the network logon service was not started.
1793	0x0701	N/A	The user's account has expired.
1794	0x0702	N/A	The redirector is in use and cannot be unloaded.
1795	0x0703	N/A	The specified printer driver is already installed.
1796	0x0704	N/A	The specified port is unknown.
1797	0x0705	N/A	The printer driver is unknown.
1798	0x0706	N/A	The print processor is unknown.
1799	0x0707	N/A	The specified separator file is invalid.
1800	0x0708	N/A	The specified priority is invalid.
1801	0x0709	N/A	The printer name is invalid.
1802	0x070A	N/A	The printer already exists.
1803	0x070B	N/A	The printer command is invalid.
1804	0x070C	N/A	The specified datatype is invalid.
1805	0x070D	N/A	The Environment specified is invalid.
1806	0x070E	N/A	There are no more bindings.
1807	0x070F	N/A	The account used is an interdomain trust account. Use your global user account or local user account to access this server.
1808	0x0710	N/A	The account used is a Computer Account. Use your global user account or local user account to access this server.
1809	0x0711	N/A	The account used is an server trust account. Use your global user account or local user account to access this server.
1810	0x0712	N/A	The name or security ID (SID) of the domain specified is inconsistent with the trust information for that domain.
1811	0x0713	N/A	The server is in use and cannot be unloaded.
1812	0x0714	N/A	The specified image file did not contain a resource section.
1813	0x0715	N/A	The specified resource type can not be found in the image file.
1814	0x0716	N/A	The specified resource name can not be found in the image file.

1815	0x0717	N/A	The specified resource language ID cannot be found in the image file.
1816	0x0718	N/A	Not enough quota is available to process this command.
1817	0x0719	N/A	No interfaces have been registered.
1818	0x071A	N/A	The server was altered while processing this call.
1819	0x071B	N/A	The binding handle does not contain all required information.
1820	0x071C	N/A	Communications failure.
1821	0x071D	N/A	The requested authentication level is not supported.
1822	0x071E	N/A	No principal name registered.
1823	0x071F	N/A	The error specified is not a valid Windows RPC error code.
1824	0x0720	N/A	A UUID that is valid only on this computer has been allocated.
1825	0x0721	N/A	A security package specific error occurred.
1826	0x0722	N/A	Thread is not cancelled.
1827	0x0723	N/A	Invalid operation on the encoding/decoding handle.
1828	0x0724	N/A	Incompatible version of the serializing package.
1829	0x0725	N/A	Incompatible version of the RPC stub.
1898	0x076A	N/A	The group member was not found.
1899	0x076B	N/A	The endpoint mapper database could not be created.
1900	0x076C	N/A	The object universal unique identifier (UUID) is the nil UUID.
1901	0x076D	N/A	The specified time is invalid.
1902	0x076E	N/A	The specified Form name is invalid.
1903	0x076F	N/A	The specified Form size is invalid
1904	0x0770	N/A	The specified Printer handle is already being waited on
1905	0x0771	N/A	The specified Printer has been deleted
1906	0x0772	N/A	The state of the Printer is invalid
1907	0x0773	N/A	The user must change his password before he logs on the first time.
1908	0x0774	N/A	Could not find the domain controller for this domain.
1909	0x0775	N/A	The referenced account is currently locked out and may not be logged on to.
2000	0x07D0	N/A	The pixel format is invalid.
2001	0x07D1	N/A	The specified driver is invalid.
2002	0x07D2	N/A	The window style or class attribute is invalid for this operation.
2003	0x07D3	N/A	The requested metafile operation is not supported.
2004	0x07D4	N/A	The requested transformation operation is not supported.
2005	0x07D5	N/A	The requested clipping operation is not supported.

2202	0x089A	N/A	The specified username is invalid.
2250	0x08CA	N/A	This network connection does not exist.
2401	0x0961	N/A	This network connection has files open or requests pending.
2402	0x0962	N/A	Active connections still exist.
2404	0x0964	N/A	The device is in use by an active process and cannot be disconnected.
3000	0x0BB8	N/A	The specified print monitor is unknown.
3001	0x0BB9	N/A	The specified printer driver is currently in use.
3002	0x0BBA	N/A	The spool file was not found.
3003	0x0BBB	N/A	A StartDocPrinter call was not issued.
3004	0x0BBC	N/A	An AddJob call was not issued.
3005	0x0BBD	N/A	The specified print processor has already been installed.
3006	0x0BBE	N/A	The specified print monitor has already been installed.
4000	0x0FA0	N/A	WINS encountered an error while processing the command.
4001	0x0FA1	N/A	The local WINS can not be deleted.
4002	0x0FA2	N/A	The importation from the file failed.
4003	0x0FA3	N/A	The backup Failed. Was a full backup done before ?
4004	0x0FA4	N/A	The backup Failed. Check the directory that you are backing the database to.
4005	0x0FA5	N/A	The name does not exist in the WINS database.
4006	0x0FA6	N/A	Replication with a non-configured partner is not allowed.
6118	0x17E6	N/A	The list of servers for this workgroup is not currently available